

# TecCom TecLocal 4.0 Installation Manual(4.0.012)

Autor Version Jonay Braun Suárez

24.04.2017 Datum

Status

Copyright © TecAlliance GmbH – Die Weitergabe dieses Dokumentes, auch auszugsweise in beliebiger Form, bedarf der schriftlichen Zustimmung der TecAlliance GmbH.

TecAlliance GmbH Steinheilstraße 10 85737 Ismaning Germany Tel: +49 89 321216 -0



# Änderungshistorie

| Source<br>Version | Target<br>Version | Date       | Name               | Comment   |
|-------------------|-------------------|------------|--------------------|---|
| 1.0               |                   | 12.12.2016 | Jonay Braun Suárez | First draft                                       |
| 2.0               |                   | 24.04.2016 | Jaroslav Markovec  | Support for Windows<br>10, Windows Server<br>2016 |

## Verteiler

| Role/Roles        | Name | Phone | E-Mail |
|-------------------|------|-------|--------|
| Writing technical |      |       |        |
| specification     |      |       |        |
| Development       |      |       |        |

Seite 2 von 26 © TecAlliance GmbH



# **Contents**

| 1 | Inte  | Intention of the document                        |   |    |  |  |  |  |  |  |
|---|---|--|---|----|--|--|--|--|--|--|
| 2 | Inst  | Installation Prerequisites4                      |   |    |  |  |  |  |  |  |
| 3 | Gen   | General requisites for TecLocal 4.0 Installation |   |    |  |  |  |  |  |  |
|   | 3.1   | Operating System Support                         |   |    |  |  |  |  |  |  |
|   | 3.2   | Requisites for operation mode/installation type  |   |    |  |  |  |  |  |  |
|   |   | 3.2.1  | Requisites for operation mode Buyer for a single user   | 4  |  |  |  |  |  |  |
|   |   | 3.2.2  | Requisites for operation mode Buyer for a multiple user | 4  |  |  |  |  |  |  |
|   |   | 3.2.3  | Requisites for operation mode Supplier                  | 4  |  |  |  |  |  |  |
| 4 | Nev   | v installa                                       | ation of TecLocal 4.0.012 as Supplier                   | 5  |  |  |  |  |  |  |
|   | 4.1   | 1 Oracle Database                                |   |    |  |  |  |  |  |  |
|   | 4.2   | Micros   | oft SQL Server Database                                 | 9  |  |  |  |  |  |  |
| 5 | Nev   | New installation of TecLocal 4.0.012 as Buyer14  |   |    |  |  |  |  |  |  |
|   | 5.1   | Single User Installation                         |   |    |  |  |  |  |  |  |
|   | 5.2   | Multi-U  | Jser Installation                                       | 19 |  |  |  |  |  |  |
| 6 | Import settings from previous version of TecLocal |  |   |    |  |  |  |  |  |  |
|   | 6.1   | Use existing settings                            |   |    |  |  |  |  |  |  |
|   | 6.2   | Ask all  | options   | 25 |  |  |  |  |  |  |
| 7 | Installer options                                 |  |   |    |  |  |  |  |  |  |
|   | 7.1   | Logging  | g of installation process                               | 25 |  |  |  |  |  |  |



#### 1 Intention of the document

This document describes the installation of TecLocal 4.0 under Microsoft Windows OS.

## 2 Installation Prerequisites

These are the requisites that need to be met for successfully install TecLocal 4.0.012

## 3 General requisites for TecLocal 4.0 Installation

In order to successfully install and use TecLocal 4.0 Microsoft .NET Framework 4.0 or above has to be installed on the target machine.

## 3.1 Operating System Support

TecLocal 4.0 can be installed and used in the following Operating Systems:

- Server Operating System: Windows Server 2008 R2

Windows Server 2012 R2

Windows Server 2016

Client Operating System: Windows 7

Windows 8.1 Windows 10

# 3.2 Requisites for operation mode/installation type

TecLocal 4.0 can be installed in two operations modes. The operation modes are the following:

- Buyer
- Supplier

The Buyer mode can be installed for:

- Single user
- Multiple user

#### 3.2.1 Requisites for operation mode Buyer for a single user

There are no additional requisites for this operation mode/installation type.

#### 3.2.2 Requisites for operation mode Buyer for a multiple user

For this installation scenario a connection with administrator credentials to Microsoft SQL Server instance is required.

#### 3.2.3 Requisites for operation mode Supplier

There are no additional requisites for this operation mode/installation type.

Seite 4 von 26 © TecAlliance GmbH




# 4 New installation of TecLocal 4.0.012 as Supplier

#### 4.1 Oracle Database

Download the latest TecLocal installer (TecLocal\_Setup\_V\_4.x.xxx.exe). Start the installation and follow the installation steps.

If Microsoft .NET Framework 4.0 or above was not installed in the target machine the following message is shown after the installation language is selected:




Install Microsoft .NET Framework 4.0 or above and then start the installation again.




Select the language for the installation wizard and click "OK"

© TecAlliance GmbH Seite 5 von 26






#### Click "Next"




Select the installation folder and click "Next"

Seite 6 von 26 © TecAlliance GmbH






Select "as Supplier" and click "Next"




Read the End-User License Agreement, then select "I accept the terms in the License Agreement" and click "Next"

© TecAlliance GmbH Seite 7 von 26





Select "Oracle" and click "Next"




Type the IP of the host where the Oracle database is located, the port used and the SID of the database, then click "Next".

Seite 8 von 26 © TecAlliance GmbH





Click "Install"



Click "Finish"


# 4.2 Microsoft SQL Server Database

Download the latest TecLocal 4.0.012 installer. Launch the installer and follow the installation steps.

© TecAlliance GmbH Seite 9 von 26




If Microsoft .NET Framework 4.0 or above was not installed in the target machine the following message is shown:



Install Microsoft .NET Framework 4.0 or above and then launch the installer again.




Select the language for the installation wizard and click "OK"




Click "Next"

Seite 10 von 26 © TecAlliance GmbH





Select the installation folder and click "Next"




Select "as Supplier" and click "Next"

© TecAlliance GmbH Seite 11 von 26






Read the End-User License Agreement, then select "I accept the terms in the License Agreement" and click "Next"




Select "SQL Server" and click "Next"

Seite 12 von 26 © TecAlliance GmbH






Type the SQL Server host or click "Browse" to search for the SQL Server hosts located in your network and then select the target SQL Server from the dropdown list. Then click "Next"




Type the database name or click "Browse" to search for the available databases located in the SQL Server host previously selected and choose from the dropdown list the correct database, then click "Next"

© TecAlliance GmbH Seite 13 von 26





Click "Install"



Click "Finish"

# 5 New installation of TecLocal 4.0.012 as Buyer

TecLocal Buyer mode has to installation types:

- Single User installation

Seite 14 von 26 © TecAlliance GmbH




- Multi-User installation

Single user installation will use Microsoft Access database for storing data. Multi-user installation requires a Microsoft SQL Server database

### 5.1 Single User Installation

Download the latest TecLocal installer (TecLocal\_Setup\_V\_4.x.xxx.exe). Start the installation and follow the installation steps.

If Microsoft .NET Framework 4.0 or above was not installed in the target machine the following message is shown after the installation language is selected:




Install Microsoft .NET Framework 4.0 or above and then start the installation again.



Select the language for the installation wizard and click "OK"

© TecAlliance GmbH Seite 15 von 26






#### Click "Next"




Select the installation folder and click "Next"

Seite 16 von 26 © TecAlliance GmbH





Select "as Buyer" and click "Next"



Select "As Sinlge-user solution", then click "Next"

© TecAlliance GmbH Seite 17 von 26






Read the End-User License Agreement, then select "I accept the terms in the License Agreement" and click "Next"



Click "Install"

Seite 18 von 26 © TecAlliance GmbH






Click "Finish"

#### 5.2 Multi-User Installation

Download the latest TecLocal installer (TecLocal\_Setup\_V\_4.x.xxx.exe). Start the installation and follow the installation steps.

If Microsoft .NET Framework 4.0 or above was not installed in the target machine the following message is shown after the installation language is selected:




Install Microsoft .NET Framework 4.0 or above and then start the installation again.

© TecAlliance GmbH Seite 19 von 26






Select the language for the installation wizard and click "OK"




Click "Next"

Seite 20 von 26 © TecAlliance GmbH






Select the installation folder and click "Next"



Select "as Buyer" and click "Next"

© TecAlliance GmbH Seite 21 von 26






Select "As Multi-user solution", then click "Next"




Read the End-User License Agreement, then select "I accept the terms in the License Agreement" and click "Next"

Seite 22 von 26 © TecAlliance GmbH






Type the SQL Server host or click "Browse" to search for the SQL Server hosts located in your network and then select the target SQL Server from the dropdown list. Then click "Next"




Type the database name or click "Browse" to search for the available databases located in the SQL Server host previously selected and choose from the dropdown list the correct database, then click "Next"

© TecAlliance GmbH Seite 23 von 26





Click "Install"




Click "Finish"

# 6 Import settings from previous version of TecLocal

If you have a previous compatible version of TecLocal installed, the installer will give you an option to import the existing settings.

Seite 24 von 26 © TecAlliance GmbH





Select whether you want to use existing settings or install the application from scratch.

# 6.1 Use existing settings

By using the existing settings you can import (take over) some installation parameters and thus reduce the number of installation dialogs. The settings that can be imported are:

- Operation mode
- Single/multiple user mode for buyer operation mode
- Copy over MS Access databases

Assumptions will be made based on the existing settings and if MS Access files are found in the database folder, they will be copied over to the new installation

## 6.2 Ask all options

By selecting all options, the installer will continue as if there was no previous version of TecLocal and thus can be configured from scratch. No Microsoft Access database will be copied over.

# 7 Installer options

There are few installer parameters that can be helpful when experiencing installation problems.

# 7.1 Logging of installation process

Complete log of the installation process can be created by using the following parameters after the setup executive name:

© TecAlliance GmbH Seite 25 von 26



TecLocal.Setup.exe /lvx <logfile>

If the installer is started with these parameters an installation log file specified in the <logfile> parameter will be created.

Seite 26 von 26 © TecAlliance GmbH